
3D-CMCC-FEM

(Coupled Model Carbon Cycle)

BioGeoChemical and Biophysical Forest Ecosystem Model

User's Guide (v.5.x.x)

(updated February 2023)



Website: www.forest-modelling-lab.com

Forest Modelling Laboratory – National Research Council of Italy

Institute for Agriculture and Forestry Systems in the Mediterranean (CNR-ISAFOM) Via Madonna Alta 128 - 06128, Perugia (PG), Italy

Lab. contacts

(forest.modelling.lab@isafom.cnr.it, 3d.cmcc.fem@gmail.com)

Alessio Collalti (Lab. Head)



Institute for Agriculture and Forestry Systems in the Mediterranean of the National Research Council of Italy (CNR- ISAFOM)
Via della Madonna Alta, 128 - 06128 Perugia (PG) Italy

Daniela Dalmonech



Institute for Agriculture and Forestry Systems in the Mediterranean of the National Research Council of Italy (CNR- ISAFOM)
Via della Madonna Alta, 128 - 06128 Perugia (PG) Italy

Gina Marano



ETH Zürich, Department of Environmental System Sciences, Chair of Forest Ecology Universitätstrasse 16, 8057 Zurich, Switzerland

Riccardo Testolin



Institute for Agriculture and Forestry Systems in the Mediterranean of the National Research Council of Italy (CNR- ISAFOM)
Via della Madonna Alta, 128 - 06128 Perugia (PG) Italy

Alessio Ribeca



Department for innovation in biological, agro-food and forest systems (DIBAF) University of Tuscia Via S. Camillo de Lellis snc, 01100 Viterbo (VT) Italy



Index

1.		Code availability4						
2.		Model description						
3.		Referencing the model						
4.		Run	the model	7				
	4.	1	Model inputs	7				
		Star	nd initialization file	8				
		Soil	initialization file	9				
		Тор	ography initialization file	.10				
		Met	teorological data file	.11				
		CO ₂	atmospheric concentration file	.12				
		Spe	cies-Parameterization file	.13				
		Sett	ings file	.17				
	4.	2	Model outputs	.20				
		Ann	nual Outputs	.20				
		Mor	nthly Outputs	.23				
		Dail	y Outputs	.24				
5.		Mar	nagement	.27				
6.		3D-0	CMCC-FEM Usage	.28				
7.		Hov	v to run and develop the 3D-CMCC-FEM	.31				
	7.	1	Code characteristics	.31				
	7.	2	Eclipse usage instruction (for developers)	.31				
		Hov	v to increase Eclipse available heap size (optional)	.32				
		Hov	v to work on Eclipse for bash scripts (optional)	.32				
	7.	3	Bash launch (for UNIX users)	.32				
8.		Que	estions or comments	.33				



1. Code availability

The **3D-CMCC-FEM** ("Three **D**imensional - **C**oupled **M**odel **C**arbon **C**ycle - **F**orest **E**cosystem **M**odel") is a computer model and is primarily a research tool, and many versions have been developed for specific purposes. The National Research Council of Italy and University of Tuscia maintain benchmark code versions for public release and update these benchmark versions periodically as new knowledge is gained on the research front. The code and executables accompanying this file represent the most recent benchmark version. The **3D-CMCC-FEM** code (any version) is copyrighted.

The 3D-CMCC-FEM is freely available only for non-commercial use. We have developed the 3D-CMCC-FEM code relying solely on open source components, in order to facilitate its use and further development by others. The 3D-CMCC-FEM is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. The 3D-CMCC-FEM code is released under the GNU General Public Licence (GPL) at: https://github.com/Forest-Modelling-Lab/3D-CMCC-FEM. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program. If not, see http://www.gnu.org/licenses/gpl.html.

The model has been developed and is maintained by the Forest Modelling Laboratory at the National Research Council of Italy, Institute for Agricultural and Forestry Systems in the Mediterranean (CNR-ISAFOM), Perugia. All source code and documents are subject to copyright © by the CNR. In case you have copied and/or modified the 3D-CMCC-FEM code overall, even in small parts of it, you may not publish data from it using the name 3D-CMCC-FEM or any 3D-CMCC-FEM variants unless you have either coordinated your usage and their changes with the developers listed below, or publish enough details about your changes so that they could be replicated.

The 3D-CMCC-FEM has been developed by: Alessio Collalti, Daniela Dalmonech and Gina Marano who are part of (or associated to) the Forest Ecology Laboratory at the National Research Council of Italy (CNR), Institute for Agricultural and Forestry Systems in the Mediterranean (ISAFOM), Via della Madonna Alta, 128, 06128 - Perugia (PG), Italy. CNR accepts no responsibility for the use of the 3D-CMCC-FEM in the form supplied or as subsequently modified by third parties. CNR disclaims liability for all losses, damages and costs incurred by any person as a result of relying on this software. Use of this software assumes agreement to this condition of use. Removal of this statement violates the spirit in which 3D-CMCC-FEM was released by CNR. The 3D-CMCC-FEM (both versions: Light Use Efficiency and the fully BioGeoChemical version). Versions 5.5.x code is open. You can get a free copy of the code online from: (GitHub Repository) https://github.com/Forest-Modelling-Lab/3D-CMCC-FEM.



User's Guide 3D-CMCC-FEM

2. Model description

The 3D-CMCC-FEM is biogeochemical, biophysical forest model that simulates the dynamics occurring in homogeneous and heterogeneous forests with different plant species, for different age, diameter and height classes. The model can reproduce forests from simple up to forests with a complex canopy structure (i.e. constituted by cohorts competing for light and water resources). The 3D-CMCC-FEM simulates carbon fluxes, in terms of gross and net primary productivity (GPP and NPP, respectively), partitioning and allocation in the main plant compartments (stem, branch, leaf, fruit, fine and coarse root, non-structural carbon) and water fluxes in terms of leaf and canopy transpiration, canopy and soil evaporation and the overall forest water balance. In the recent versions, nitrogen fluxes and allocation, in the same carbon pools, are also reproduced. The 3D-CMCC-FEM also takes into account management practices, as thinning and harvest, to predict their effects on forest growth and carbon sequestration. The 3D-CMCC-FEM is written in C-programming language and divided into several subroutines. To run the model, some input data are required. The meteorological forcing variables, on a daily time step, are represented by average, minimum and maximum air temperature, shortwave solar radiation, precipitation, vapor pressure deficit (or relative humidity). The model also needs some basic information about soil, such as soil depth and texture (clay, silt and sand fractions), as well as the forest stand information referred to plant species, ages, diameters, heights and stand density. An additional input is represented by species-specific eco-physiological data for the model parameterization. Copyright © 2023, Forest Modelling Laboratory – 3D-CMCC-FEM. All rights reserved.

Referencing the model 3.

If you use 3D-CMCC-FEM in your research, based on the version used, please include the following acknowledgments in the relevant manuscript:

"3D-CMCC-FEM, Version 5.x.x was provided by Alessio Collalti and Daniela Dalmonech, or others, from Forest Modelling Lab. | National Research Council of Italy, Institute for Agricultural and Forestry Systems in the Mediterranean (CNR-ISAFOM);

Please also reference the following citation(s) as the most recent and complete description of the current model versions:

v.4.0 (not more in use)

- "Sviluppo di un modello dinamico ecologico-forestale per foreste a struttura complessa". A. Collalti, 2011. Ph.D. Thesis, Ph.D. Riccardo Valentini. University of Tuscia, http://dspace.unitus.it/bitstream/2067/2398/1/acollalti_tesid.pdf, (in Italian)
- "A process-based model to simulate growth and dynamics in forests with complex structure: evaluation and use of 3D-CMCC Forest Ecosystem Model in a deciduous forest in Central Italy". A. Collalti, L. Perugini, T. Chiti, Modelling 2014. Nolè, G. Matteucci, **Ecological** https://doi.org/10.1016/j.ecolmodel.2013.09.016.

<u>v.5.1.1 (not more in use)</u>

"Validation of 3D-CMCC Forest Ecosystem Model (v.5.1) against eddy covariance data for 10 European forest sites". A. Collalti, S. Marconi, A. Ibrom, C. Trotta, A. Anav, E. D'Andrea, G. Matteucci, L. Montagnani, B. Gielen, I. Mammarella, T. Grünwald, A. Knohl, F. Berninger, Y. Zhao, R. Valentini and M. Santini, Geoscientific Model



Development, 2016. https://doi.org/10.5194/gmd-9-479-2016.

v.PSM (not more in use)

- "Assessing NEE and Carbon Dynamics among 5 European Forest types: Development and Validation of a new Phenology and Soil Carbon routines within the process oriented 3D-CMCC-Forest-Ecosystem Model", S. Marconi, Jan 2013, *University of Tuscia*, *M.Sc. Thesis*, M.Sc. Advisors: R. Valentini, T. Chiti, A. Collalti.

- "The Role of Respiration in Estimation of Net Carbon Cycle: Coupling Soil Carbon Dynamics and Canopy Turnover in a Novel Version of 3D-CMCC Forest Ecosystem Model". S. Marconi, T. Chiti, A. Nolè, R. Valentini and A. Collalti. *Forests* 2017. https://doi.org/10.3390/f8060220.

v.5.3.3-ISIMIP

- "Thinning can reduce losses in carbon use efficiency and carbon stocks in managed forests under warmer climate". Collalti A., Trotta C., Keenan T.F., Ibrom A., Lamberty B.B., Gröte R., Vicca S., Reyer C.P.O., Migliavacca M., Veroustraete F., Anav A., Campioli M., Scoccimarro E., Šigut L., Grieco E., Cescatti A., and Matteucci G., Journal of Advances in Modelling Earth System 2018. https://doi.org/10.1029/2018MS001275.
- "Climate change mitigation by forests: a case study on the role of management on carbon dynamics of a pine forest in South Italy". Pellicone G., August 2018, *University of Tuscia*, *Ph.D. Thesis*, Ph.D. Advisors: G. Scarascia-Mugnozza, G. Matteucci, A. Collalti.

<u>v.5.3</u>

"The sensitivity of the forest carbon budget shifts across processes along with stand development and climate change". Collalti A., Thornton P.E., Cescatti A., Rita A., Borghetti M., Nolè A., Trotta C., Ciais P., Matteucci G. *Ecological Applications* 2018. https://doi.org/10.1002/eap.1837.

v.5.5 (and v.5.5-ISIMIP)

- "Plant respiration: Controlled by photosynthesis or biomass?" Collalti A., Tjoelker M.G., Hoch G., Mäkelä A.,
 Guidolotti G., Heskel M., Petit G., Ryan M.G., Battipaglia G., Matteucci G., Prentice I.C. *Global Change Biology* 2020, https://doi.org/10.1111/gcb.14857
- "Simulating the effects of thinning and species mixing on stands of oak (Quercus petrea (Matt.) Liebl. / Quercus robur L.) and pine (Pinus sylvestris L.) across Europe", Engel M., VVospernik S., Toigo M., Morin X., Tomao A., Trotta C., Steckel M., Barbati A., Nothdurft A. Pretzsch H., del Rio M., Skrzyszewski J., Ponette Q., Lof M., Jansons A., Brazaitis G., *Ecological Modelling*, 2021, https://doi.org/10.1016/j.ecolmodel.2020.109406
- "Accuracy, realism and general applicability of European forest models" Mahnken, M., Cailleret M., Collalti A., Trotta C., Biondo C., D'Andrea E., Dalmonech D., Marano G., Mäkelä A., ..., Reyer C.P.O., *Global Change Biology*, 2022, https://doi.org/10.1111/gcb.16384
- "Feasibility of enhancing carbon sequestration and stock capacity in temperate and boreal European forests via changes to forest management", Dalmonech D., Marano G., Amthor J., Cescatti A., Lindner M., Trotta C., Collalti A., *Agricultural and Forest Meteorology*, 2022 https://doi.org/10.1016/j.agrformet.2022.109203

<u>v.5.6</u>

- "Simulating diverse forest management in a changing climate on a Pinus nigra subsp. Laricio plantation in Southern Italy", Testolin R., Dalmonech D., Marano G., D'Andrea E., Matteucci G., Noce S., Collalti A., *Science of the Total Environment*, 2023 https://doi.org/10.1016/j.scitotenv.2022.159361

If you have made any significant modifications to the code, please mention them in your manuscript.



9 eg

This User's Guide is the only documentation released with 3D-CMCC-FEM.

The code itself contains extensive internal documentation, and users with specific questions about the algorithms used to estimate particular processes should read the comments in the appropriate source code files.

The file treemodel.c contains references to all the core science routines and is a good starting point for this kind of inquiry. The files matrix.c defines the data structures that are used to pass information between the process modules and includes both a short text description and the units for each internal variable.

Shall you have questions about the code, appropriate model applications, possible programming errors, etc., please read this entire guide first, and then feel free to contact us.

4. Run the model

4.1 Model inputs

The 3D-CMCC-FEM model uses at least seven input files which are mandatory when not expressly defined as optional. These files must be necessarily provided to run the model:

- "setting" file;
- "stand" file;
- "species" file;
- "meteo" file;
- "soil" file;
- "topo" file;
- "CO2" file;
- "Ndep" file (optional);

A brief description of all files is given first, followed by detailed discussions of each file.

Be sure to set the right arguments passed to the project and go into bin directory:

```
cd bin
```

Run executable (e.g. in Bash Shell) with default parameters:

```
./3D-CMCC-Forest-Model -i input -o output -p parameterization -d sitename_stand.txt -m sitename_meteo_firstyear.txt -s sitename_soil.txt -t sitename topo.txt -c sitename settings.txt -k CO2 hist.txt > log.txt
```



Stand initialization file

```
/home/alessio/git/3D-CMCC-FEM/softwa
    Modifica Cerca Visualizza Documento Aiuto
l Year,x,y,Age,Species,Management,N,Stool,AvDBH,Height,Wf,Wrc,Wrf,Ws,Wbb,Wres,Lai
 1944,0,0,23,Fagussylvatica,T,1767,0,3.619168081,6.666049802,0,0,0,0,0,0,0
3 1945,0,0,24,Fagussylvatica,T,1525,0,4.041901639,7.031160656,0,0,0,0,0,0
 1946,0,0,25,Fagussylvatica,T,1525,0,4.459383607,7.391298361,0,0,0,0,0,0,0 1947,0,0,26,Fagussylvatica,T,1525,0,4.817278689,7.747770492,0,0,0,0,0,0,0
 1948,0,0,27,Fagussylvatica,T,1326,0,5.128280543,8.105067873,0,0,0,0,0,0
 1949,0,0,28,Fagussylvatica,T,1326,0,5.535475113,8.460180995,0,0,0,0,0,0,0
 1950,0,0,29,Fagussylvatica,T,1326,0,5.961357466,8.814479638,0,0,0,0,0,0,0
 1951,0,0,30,Fagussylvatica,T,1162,0,6.397521515,9.167340792,0,0,0,0,0,0,0
1952,0,0,31,Fagussylvatica,T,1162,0,6.784535284,9.516583477,0,0,0,0,0,0,0
 1953,0,0,32,Fagussylvatica,T,1162,0,7.173580034,9.859578313,0,0,0,0,0,0,0
 1954,0,0,33,Fagussylvatica,T,1023,0,7.552385142,10.20050831,0,0,0,0,0,0
 1955,0,0,34,Fagussylvatica,T,1023,0,7.9271261,10.54035191,0,0,0,0,0,0
 1956,0,0,35,Fagussylvatica,T,1023,0,8.232072336,10.87387097,0,0,0,0,0,0,0 1957,0,0,36,Fagussylvatica,T,906,0,8.591523179,11.20501104,0,0,0,0,0,0,0,0
 1958,0,0,37,Fagussylvatica,T,906,0,8.940905077,11.530883,0,0,0,0,0,0,0
  1959,0,0,38,Fagussylvatica,T,906,0,9.270640177,11.85339956,0,0,0,0,0,0,0
  960.0.0.39.Fagussylvatica.T.806.0.9.61235732.12.17648883.0.0.0.0.0.0.0.
```

Figure 1 | Example of stand file

The first required input file is called the "sitename_stand.txt". It provides information about the stand conditions.

Example for a cell resolution of 100×100 meters cell X = 0, Y = 0:

```
Year, x, y, Age, Species, Management, N, Stool, AvDBH, Height, Wf, Wrc, Wrf, Ws, Wbb, Wres, Lai 1944, 0, 0, 23, Fagussylvatica, T, 1767, 0, 3.619168081, 6.666049802, 0, 0, 0, 0, 0, 0, 0 1945, 0, 0, 24, Fagussylvatica, T, 1525, 0, 4.041901639, 7.031160656, 0, 0, 0, 0, 0, 0, 0 1946, 0, 0, 25, Fagussylvatica, T, 1525, 0, 4.459383607, 7.391298361, 0, 0, 0, 0, 0, 0, 0 1947, 0, 0, 26, Fagussylvatica, T, 1525, 0, 4.817278689, 7.747770492, 0, 0, 0, 0, 0, 0, 0 1948, 0, 0, 27, Fagussylvatica, T, 1326, 0, 5.128280543, 8.105067873, 0, 0, 0, 0, 0, 0, 0 1949, 0, 0, 28, Fagussylvatica, T, 1326, 0, 5.535475113, 8.460180995, 0, 0, 0, 0, 0, 0, 0 1950, 0, 0, 29, Fagussylvatica, T, 1326, 0, 5.961357466, 8.814479638, 0, 0, 0, 0, 0, 0, 0
```

The text file must be created following this logic architecture

- for each tree height class define the number of age classes and their values
- -- for each height->dbh class

Year

- --- for each height->dbh->age class
- ---- for each height->dbh->age->species class define its state variables:

Comments are allowed in the parameter file. Comments can appear almost anywhere, must begin with two forward slash characters '//', at the end of the line. Example parameter files are provided. Parameter definition and its value must be separated by one-tab character.

<u>IMPORTANT</u>: Values are referred to the SIZECELL dimensions specified in the setting.txt file (e.g. if SIZECELL = 100 meters variable values refer to tCha⁻¹).

NOTE: for easiest simulations you can also use the "average tree" concept which simplify (a lot) simulations and analyses (see above).

 ∞

Раде

Reference year for stand data



X,Y Cell position

Age of tree(s) (in years)

Species Name of species (as exactly as the name of species file)

Management Tree habitus (T = timber; C = Coppice)

N Number of trees (for that class if more than one class) per cell

*Stool Number of stool per cell

AvDBH Average diameter at breast height (for that class if more than one class) (in cm)

Height Tree height (for that class if more than one class) (in m)

*Wf Foliage biomass (for that class if more than one class) (in tDM ha⁻¹)

*Wrc Coarse root biomass (for that class if more than one class) (in tDM ha⁻¹)

*Ws Stem biomass (for that class if more than one class) (in tDM ha⁻¹)

*Wbb Branch and Bark biomass (for that class if more than one class) (in tDM ha⁻¹)

*Wres Reserve (for that class if more than one class) (in tC ha⁻¹)

*LAI Leaf Area Index (for that class if more than one class) (in m² m⁻²)

Soil initialization file

Figure 2 | Example of soil characteristic file

The fourth required input file is "*sitename_soil.txt*". It contains information about soil and fertility of the test site.

Comments are allowed in the parameter file. Comments can appear almost anywhere, must begin with two forward slash characters '//', at the end of the line.

It contains the following parameters:

X,Y,LANDUSE,LAT,LON,CLAY_PERC,SILT_PERC,SAND_PERC,SOIL_DEPTH,FR,FN0,FNN,M,LITTER C, LITTERN,SOILC,SOILN,DEADWOODC 0,0,F,49.3,18.32,20.63,20.63,58.74,80,0.65,0.5,0.5,0.2,-9999,-9999,-9999,-9999



^{*}Parameters not mandatory, mostly used from developers or in specific model versions under development

X,Y Cell position **LANDUSE** See LANDUSE section LAT Latitude (in °) LONG Longitude (in °) CLAY_PERC Soil clay (in %) SILT_PERC Soil silt (in %) SAND_PERC Soil sand (in %) SOIL_DEPTH Soil depth (in cm) FR Fertility rating (dim) (only LUE version) Value of fertility modifier when FR=0 (dim) FN0 M0 Value of 'm' when FR=0 (dim) Litter carbon (in tC ha⁻¹) (Optional) *LITTERC Litter nitrogen (in tN ha⁻¹) (Optional) *LITTERN Soil carbon (in tC ha⁻¹) (Optional) *SOILC Soil nitrogen (in tN ha⁻¹) (Optional) *SOILN *DEADWOODC Dead wood carbon (in tC ha⁻¹) (Optional)

Topography initialization file



Figure 3| Example of topography file

The fifth required input file is "*sitename_topo.txt*". It contains information about topography of the test site.

Comments are allowed in the parameter file. Comments can appear almost anywhere, must begin with two forward slash characters '//', at the end of the line.

It contains the following parameters:

X,Y,40



^{*}Parameters not mandatory, mostly used from developers or in specific model versions under development

X,Y Cell position

ELEV Elevation (in m)

Meteorological data file

~									/home/als	essio/ait/3t)-CIVICC-FEI	M/software	/3D-CMCC	-Forest-Mod	lel/inout/Sc	91/151/NIS
File	Modifica	Cerca	Visualizza	Documento	Aiuto											
	Year	Month	n days		Ta f	Tmax	Tmin	RH f	Ts f	Precip	SWC	LAI	ET	WS f		
	1950	1	1			-2.8258			-9999	3.3086	-9999	-9999	-9999	9.4395		
	1950	î	2			-1.6239			-9999	2.7083	-9999	-9999	-9999	6.1997		
	1950	ī	3			-1.9484			-9999	2.319	-9999	-9999	-9999	5.3645		
	1950	1	4	0.99111				-3.0299		-9999	0	-9999	-9999	-9999	3.2713	
	1950	ī	5	0.5722			0.81442			99.265	-9999	1.6465	-9999	-9999	-9999	2.919
	1950	1	6	0.60553					98.878	-9999	1.4674	-9999	-9999	-9999	3.0447	
	1950	ī		0.76504			0.863	- -1.4387		-9999	1.5422	-9999	-9999	-9999	3.3145	
	1950	1	8	1.4118				-3.2434		-9999	0	-9999	-9999	-9999	2.6675	
10	1950	1		0.77171	-2.2033	-0.80207	7	-3.246	99.393	-9999		-9999	-9999	-9999	3.7197	
11	1950		10	1.0098	-2.0168	-0.51813	3	-3.17	99.493	-9999		-9999	-9999	-9999	0.70707	
12	1950		11	1.0416	-2.3873	-1.1976	-3.3213	96.823	-9999		-9999	-9999	-9999	3.6825		
13	1950		12	1.6242	-4.6921	-2.6279	-6.7933	98.563	-9999		-9999	-9999	-9999	4.7061		
14	1950		13	1.2623	-6.2513	-3.359	-7.7293	98.922	-9999		-9999	-9999	-9999	4.3768		
15	1950		14	0.47107	-0.159	2.6675	-4.3082	96.418	-9999	2.4672	-9999	-9999	-9999	6.361		
	1950		15	0.56819			0.04409		98.038	-9999	5.4604	-9999	-9999	- 9999	1.4197	
	1950		16	0.62422			-0.0534		88.423	-9999	4.4559	-9999	-9999	-9999	8.1887	
	1950		17	0.40307			0.35574		-9999	1.909	-9999	-9999	-9999	3.8607		
	1950	1	18	0.90507		3.038	0.71676		-9999	1.6136	-9999	-9999	-9999	6.745		
	1950	1	19	1.4716	-0.8953		-3.1815		-9999	0	-9999	-9999	-9999	2.0056		
	1950		20	2.6245		-1.8488			-9999	0	-9999	-9999	-9999	4.4033		
	1950		21	1.908		-2.2712			-9999	0	-9999	-9999	-9999	7.1648		
	1950	1	22			0.86532			-9999	2.6142	-9999	-9999	-9999	5.9298		
	1950	1	23	1.1118	-0.32758		0.40042			95.205	-9999	2.5775	-9999	-9999	-9999	5.958
	1950	1	24	0.67123			0.18493			-9999	3.2684	-9999	-9999	-9999	5.9651	
	1950		25	1.1188		-0.97327		-5.3197		-9999	0	-9999	-9999	-9999	10.245	
	1950		26	2.0437		-4.4261			-9999	0	-9999	-9999	-9999	10.107		
	1950		27	0.84743					-9999	2.7738	-9999	-9999	-9999	8.8028		
	1950 1950	1	28 29	1.2803 1.2476		-3.8685 -2.0745			-9999 -9999	3.1565 2.4422	-9999 -9999	-9999 -9999	-9999 -9999	4.8892 7.9852		
	1950		29 30	0.85406			-5.0812		-9999	3.6135	-9999	-9999	-9999	9.9116		
	1950		31			-4.6268			-9999	4.7849	-9999	-9999	-9999	11.841		
	1950	2	1	1.6123		-6.0981			-9999	2.3175	-9999	-9999	-9999	9.8185		
	1950	2	2	2.438		-5.4406			-9999	0	-9999	-9999	-9999	8.1005		
	1950	2	3	2.0056	-6.39		-7.6904		-9999	0	-9999	-9999	-9999	6.2946		
30	1050	-	4	2 542		7 4224			0000	0	0000	0000	0000	6 0146		

Figure 4| Example of meteorological forcing file

The second required input file is the meteorological data file, which is named using the start year of simulation (e.g. "sitename_meteo.txt"), containing the daily meteorological data.

Years of simulation depends on the number years included in the met file.

Some met data are mandatory: temperature, precipitation, vapor pressure deficit (or relative humidity) and short-wave solar radiation, whereas others are optional.

If the model runs in "spatial version" daily or monthly LAI values are mandatory otherwise they are not considered in processes. Each variable must be separated by one-tab character. Model considers leap years, so 29th of February has to be included.

Example for year 2007-2xxx in daily version:

Year	Month	n_days	Rg_f	Ta_f	Tmax	Tmin	VPD_f	Ts_f	Precip	SW	LAI	ET	WS_f
2007	1	1	6.1	-9999*	10.4	5.8	0.2	6.3	0.2	0.27	-9999*	-9999*	125.3
2007	1	2	6.2	-9999*	9.9	3.1	0.3	3.3	0	0.39	-9999*	-9999*	126.6
2007	1	3	5.8	-9999*	10	1.9	0.1	0.5	0	0.2	-9999*	-9999*	124.4

^{*}NO DATA = -9999

It contains the following variables:



Rg_f	Mean daily global radiation (MJ m ⁻² day ⁻¹)
Ta_f	Daily Average temperature (°C)
Tmax	Daily Maximum temperature (°C)
Tmin	Daily Minimum temperature (°C)
VPD_f or RH_f	Daily Vapour Pressure Deficit (mbar-hPa) or Relative Humidity (%)
Ts_f	Daily Soil temperature (°C)
Precip	Cumulated daily precipitation (mm day ⁻¹)
*SWC	Soil Water Content (mm m ⁻²)
*LAI	Leaf Area Index (m ² m ⁻²) (Only inspatial version)
*ET	Evapotranspiration (mm m ⁻² day ⁻¹)
*WS_f	Windspeed (m sec ⁻¹)

^{*}Parameters not mandatory, mostly used from developers or in specific model versions under development NOTE: missing data (-9999) in mandatory variables may lead the model to interrupt execution.

CO₂ atmospheric concentration file



Figure 5 | Example of atmospheric CO_2 concentration forcing file

Species-Parameterization file




Figure 6 | Example of species-specific parameterization file

The parameterization file is the species eco-physiological constants file, named with specie to simulate (e.g. "Fagussylvatica.txt").

Comments are allowed in the parameter file. Comments can appear almost anywhere, must begin with two forward slash characters '//', at the end of the line.

Example parameter files are provided. Parameter definition and its value must be separated by one-tab character.

It contains the following species-specific parameters:

LIGHT_TOL	Light Tolerance: 4 = very shade intolerant (canopy coverage = 90%), 3 = shade intolerant (canopy coverage 100%), 2 = shade tolerant (canopy coverage = 110%), 1 = very shade tolerant (canopy coverage = 120%)	
	0.1 = deciduous broadleaf,	
PHENOLOGY	0.2 = deciduous needle leaf,	
	1.1 = broad leaf evergreen,	
	1.2 = needle leaf evergreen	
ALPHA	Canopy quantum efficiency (molC molPAR ⁻¹)	(
EPSILONgCMJ	Light Use Efficiency (gC MJ ⁻¹) (used if ALPHA is not available)	•
K	Extinction coefficient for absorption of PAR by canopy	
ALBEDO	Canopy albedo	



INT COEFF Precipitation interception coefficient

SLA_AVG0 Average Specific Leaf Area m² KgC⁻¹ for sunlit/shaded leaves (juvenile)

SLA AVG1 Average Specific Leaf Area m² KgC⁻¹ for sunlit/shaded leaves (mature)

TSLA Age at which $SLA_AVG = (SLA_AVG1 + SLA_AVG0)/2$

SLA_RATIO (DIM) ratio of shaded to sunlit projected SLA

LAI_RATIO (DIM) all-sided to projected leaf area ratio

FRACBBO Branch and Bark fraction at age 0 (m² Kg⁻¹)

FRACBB1 Branch and Bark fraction for mature stands (m² Kg⁻¹)

TBB Age at which fracBB = (FRACBB0 + FRACBB1)/2

RHOO Minimum Basic Density for young Trees (tDM m⁻³)

RHO1 Maximum Basic Density for mature Trees (tDM m⁻³)

TRHO Age at which rho = (RHOMIN + RHOMAX)/2

FORM_FACTOR Stem form factor (adim)

COEFFCOND Define stomatal response to VPD in m sec⁻¹

BLCOND Canopy Boundary Layer conductance m sec⁻¹

MAXCOND Maximum Leaf Conductance in m sec⁻¹

CUTCOND Cuticular conductance in m sec⁻¹

MAXAGE Maximum tree age (years)

RAGE Relative Age to give fAGE = 0.5

NAGE Power of relative Age in function for Age

GROWTHTMIN Minimum temperature for growth °C

GROWTHTMAX Maximum temperature for growth °C

GROWTHTOPT Optimum temperature for growth °C

GROWTHSTART Thermic sum value for starting growth in °C

MINDAYLENGTH Minimum day length for phenology (days)

SWPOPEN Soil water potential open (MPa)

SWPCLOSE Soil water potential close (MPa)

Allocation parameter control the sensitivity of allocation to changes in water and light OMEGA CTEM

availability

SOCTEM Parameter controlling allocation to stem

ROCTEM Parameter controlling allocation to root

FOCTEM Parameter controlling allocation to foliage



FRUIT PERC %age of NPP to fruit

*CONES_LIFE_SPAN Life span for cones (years)

FINE_ROOT_LEAF Allocation new fine root C:new leaf (ratio)

STEM_LEAF Allocation new stem C:new leaf (ratio)

COARSE_ROOT_STEM Allocation new coarse root C:new stem (ratio)

LIVE_TOTAL_WOOD Allocation new live wood C:new total wood C (ratio)

N_RUBISCO Fraction of leaf N in Rubisco (ratio)

CN_LEAVES CN of leaves (kgC kgN⁻¹)

CN_FALLING_LEAVES CN of leaf litter (kgC kgN⁻¹)

CN_FINE_ROOTS CN of fine roots (kgC kgN⁻¹)

CN_LIVEWOODS CN of live woods (kgC kgN⁻¹)

CN_DEADWOOD CN of dead woods (kgC kgN⁻¹)

*LEAF_LITT_LAB_FRAC leaf litter labile fraction (dimension lees)

*LEAF_LITT_CEL_FRAC leaf litter cellulose fraction (dimension lees)

*LEAF_LITT_LIGN_FRAC leaf litter lignin fraction (dimension lees)

*FROOT_LITT_LAB_FRAC fine root litter labile fraction (dimension lees)

*FROOT_LITT_CEL_FRAC fine root litter cellulose fraction (dimension lees)

*FROOT LITT LIGN FRAC fine root litter lignin fraction (dimension lees)

*DEADWOOD_CEL_FRAC dead wood litter cellulose fraction (dimension lees)

*DEADWOOD_LIGN_FRAC dead wood litter lignin fraction (dimension lees)

BUD_BURST Days of bud burst at the beginning of growing season (only for deciduous) (days)

LEAF_FALL_FRAC_GROWING Proportions of the growing season of leaf fall

LEAF_FINEROOT_TURNOVER Average yearly leaves and fine root turnover rate

LIVEWOOD_TURNOVER Annual yearly live wood turnover rate

SAPWOOD_TURNOVER Annual yearly sapwood turnover rate

DBHDCMAX Maximum dbh crown diameter relationship when minimum density

DBHDCMIN Minimum dbh crown diameter relationship when maximum density

SAP A a coefficient for sapwood

SAP B b coefficient for sapwood

SAP_LEAF Sapwood/max leaf area ratio in pipe model (m² m⁻²)

SAP_WRES Sapwood-Reserve biomass ratio used if no Wres data are available



STEMCONST P Constant in the stem mass vs. diameter relationship

STEMPOWER_P Power in the stem mass vs. diameter relationship

CRA Chapman-Richards a parameter (maximum height, meter)

CRB Chapman-Richards b parameter

CRC Chapman-Richards c parameter

*HDMAX A A parameter for Height (m) to Base diameter (m) ratio MAX

*HDMAX_B B parameter for Height (m) to Base diameter (m) ratio MAX

*HDMIN_A A parameter for Height (m) to Base diameter (m) ratio MIN

*HDMIN_B B parameter for Height (m) to Base diameter (m) ratio MIN

*CROWN_FORM_FACTOR Crown form factor (0 = cylinder, 1 = cone, 2 = sphere, 3 = ellipsoid)

*CROWN A Crown a parameter

*CROWN_B Crown b parameter

*MAXSEED Maximum seeds number (see TREEMIG)

*MASTSEED Masting year (see TREEMIG)

*WEIGHTSEED Single fruit weight in g

*SEXAGE Age for sexual maturity

*GERMCAPACITY Germinability rate (%)

ROTATION Rotation for final harvest (based on tree age)

THINNING Thinning regime (based on year simulation)

THINNING_REGIME Thinning regime (0 = above, 1 = below)

THINNING_INTENSITY Thinning intensity (% of Basal Area N-tree to remove⁻¹)



^{*}Parameters not mandatory, mostly used from developers or in specific model versions under development

User's Guide 3D-CMCC-FEM

Settings file

```
/home/alessio/git/3D-CMCC-FEM/software/3D-CMCC-Forest-Model/input/Soroe/ISIMIP/Ff/Soroe_settings_ISIMII
File Modifica Cerca Visualizza Documento Aiuto
                                                                                                                                                                Aiuto

//Must be 'f' for FEM version or 'b', for BGC version for FOREST LANDUSE

//Must be 's' or 'u', spatial or unspatial

//Must be 'm' or 'd', monthly or daily

//Must be 'on' or 'off'

//Number of years for spinup

//Must be 'on' or 'off'

//Starting year simulation

//Ending year simulation

//Year to restart

//Must be 'on' (FvCB) or '1' (LUE) for photosynthesis approach

//Must be 'on' or 'off'

//When Co2 trans = var, year at which fix [CO2]

//Must be 'on' or 'off'

//Photosynthesis temperature acclimation Must be 'on' or 'off'

//Old temperature acclimatation Must be 'on' or 'off'

//Must be 'on' or 'off'

//Must be 'on' or 'off'

//First year of management

//Prognostic autotrophic respiration, Must be 'on' or 'off', if off Y values are used

//Its value must be within 10 and 100 (unity measure is meter: 10 = 10x10 = 100m^2)

//Fixed_Aut Resp_rate Assimilate use efficiency-Respiration rate-GPP/NPP

//CO2 concentration refers to 2000 as ISIMIP PROTOCOL

//½ increment

//0.1 Minimum fraction of asw based on maxasw (wilting point) (unchanged)
     SITENAME Soroe
VERSION f
       SPATIAL u
      TIME d
SPINUP off
SPINUP_YEARS 6000
      STANDTIEARS SOUD
SCREEN_OUTPUT OFF
DEBUG_OUTPUT OF
DAILY_OUTPUT ON
MONTHLY_OUTPUT OFF
ANNUAL_OUTPUT OFF
SOIL_OUTPUT OFF
     NETCDF_OUTPUT off
YEAR_START 1950
YEAR_END 2099
YEAR_RESTART off
      PSN_mod 0
CO2_trans on
      YEAR_START_CO2_FIXED -9999
Ndep_fixed on
       Photo accl on
       regeneration off
       management var
YEAR_START_MANAGEMENT 2020
      Progn_Aut_Resp on
SIZECELL 100
      Y 0.48
CO2CONC 368.865
      COZCONC 368.865
COZ INCR 0.01
INIT FRAC MAXASW 1
TREE LAYER LIMIT 3
SOIL LAYER 1
                                                                                                                                                                    //Co concentration refers to 2000 as isimip profocol
//1% increment
//0.1 Minimum fraction of asw based on maxasw (wilting point) (unchanged)
//define differences among tree heights in meters classes to define number of layers in unspatial version
//define soil layer/s to consider
      MAX_LAYER_COVER 1.2
THINNING REGIME Above
REPLANTED_SPECIES Fagussylvatica
REPLANTED_MANAGEMENT T
                                                                                                                                                                  // thinning regime (Above or Below)
// species name of replanted trees (mandatory)
// (T) management of replanted trees (should be only T)(mandatory)
// number of replanted trees (mandatory)
// (yr) age of replanted trees (mandatory)
// (m) average dbh of replanted trees (mandatory)
// (m2/m2) lai for replanted trees (mandatory)
// (tDM/ha) stem biomass of replanted trees (optional)
// (tDM/ha) stem biomass of replanted trees (optional)
// (tDM/ha) fine root biomass of replanted trees (optional)
// (tDM/ha) leaf biomass of replanted trees (optional)
// (tDM/ha) branch biomass of replanted trees (optional)
Figure 7 | Fxamples of settings file
      REPLANTED_TREE 6000
REPLANTED_AGE 4
REPLANTED_AVDBH 1
REPLANTED_LAI 0
       REPLANTED HEIGHT 1.3
       REPLANTED_WS 0
REPLANTED_WCR 0
REPLANTED_WFR 0
          REPLANTED WL 0
```

Figure 7 | Examples of settings file

It contains the following setting parameters:

SITENAME	Name of site
VERSION	Must be 'f' for FEM version or 'b', for BGC version for FOREST LANDUSE
SPATIAL	Must be 's' or 'u', spatial or un-spatial
TIME	Must be 'm' or 'd', monthly or daily
SPINUP	Must be 'on' or 'off'
SPINUP_YEARS	Number of years for spin-up (under development)
SCREEN_OUTPUT	Must be 'on' or 'off'
DEBUG_OUTPUT	Must be 'on' or 'off'
DAILY_OUTPUT	Must be 'on' or 'off'
MONTHLY_OUTPUT	Must be 'on' or 'off'
ANNUAL_OUTPUT	Must be 'on' or 'off'
SOIL_OUTPUT	Must be 'on' or 'off'
NETCDF_OUTPUT	Must be 'off'



YEAR_START Starting year simulation

YEAR_END Ending year simulation

YEAR_RESTART Year to restart. Must be 'off'

PSN_mod Must be '0' (FvCB version) or '1' (LUE version) for photosynthesis approach

CO2 trans Must be 'on' or 'off'

YEAR_START_CO2_FIXED -9999 . When Co2_trans = var, year at which fix [CO2]

*Ndep fixed Must be 'on' or 'off' (under development)

Photo_accl Photosynthesis temperature acclimation Must be 'on' or 'off'

Resp accl Q₁₀ temperature acclimation. Must be 'on' or 'off'

*regeneration Must be 'on' or 'off'

management Must be 'on', 'off', or 'var' (see below for differences)

YEAR_START_MANAGEMENT First year of management

Progn_Aut_Resp Prognostic autotrophic respiration. Must be 'on' or 'off', if off Y values are used

SIZECELL Its value must be within 10 and 100 (is meter: $10 = 10 \times 10 = 100 \text{ m}^2$)

Y Assimilate use efficiency-Respiration rate-NPP/GPP

CO2CONC CO₂ concentration refers to 2000

CO2_INCR 1% increment in [CO₂]

INIT_FRAC_MAXASW 0.1 Minimum fraction of Available Soil Water (ASW) based on maxASW (wilting point)

TREE_LAYER_LIMIT Define differences among tree heights in meters classes to define a new layer

*SOIL_LAYER Define soil layer(s) to consider

THINNING REGIME Thinning regime (Above or Below)

REPLANTED SPECIES Species name of replanted trees (mandatory)

*REPLANTED_MANAGEMENT (T) management of replanted trees (should be only T) (mandatory)

REPLANTED_TREE Number of replanted trees (mandatory)

REPLANTED_AGE (yr) age of replanted trees (mandatory)

REPLANTED_AVDBH (cm) average dbh of replanted trees (mandatory)

*REPLANTED LAI (m²m⁻²) LAI for replanted trees (mandatory for evergreen useless for deciduous)

REPLANTED_HEIGHT (m) height of replanted trees (mandatory)

*REPLANTED WS (tDM ha⁻¹) stem biomass of replanted trees (optional)



e 18

*REPLANTED WCR (tDM ha⁻¹) coarse root biomass of replanted trees (optional)

*REPLANTED WFR (tDM ha⁻¹) fine root biomass of replanted trees (optional)

*REPLANTED WL (tDM ha⁻¹) leaf biomass of replanted trees (optional for evergreen if LAI!= 0,

otherwise useless)

*REPLANTED_WBB (tDM ha⁻¹) branch biomass of replanted trees (optional)

*REGENERATION_SPECIES NOT USED it comes from species that produces seeds

*REGENERATION_MANAGEMENT (T) management of replanted trees (should be only T) (mandatory)

*REGENERATION_N_TREE number of replanted trees (mandatory) (NOT USED)

*REGENERATION AGE (yr) age of regeneration trees (mandatory) (SHOULD BE ALWAYS 1)

*REGENERATION_AVDBH (cm) average dbh of regeneration trees (mandatory)

*REGENERATION LAI (m²m⁻²) LAI for regeneration trees (mandatory for evergreen, useless for deciduous)

*REGENERATION_HEIGHT (m) height of replanted trees (mandatory)

*REGENERATION_WS (tDM ha⁻¹) stem biomass of regeneration trees (optional)

*REGENERATION WCR (tDM ha⁻¹) coarse root biomass of regeneration trees (optional)

*REGENERATION_WFR (tDM ha⁻¹) fine root biomass of regeneration trees (optional)

*REGENERATION_WL (tDM ha⁻¹) leaf biomass of regeneration trees (optional for evergreen if LAI!= 0,

otherwise useless)

*REGENERATION WBB (tDM ha⁻¹) branch biomass of regeneration trees (optional)

*PRUNING Must be 'on' or 'off'

*IRRIGATION Must be 'on' or 'off'



^{*}Parameters not mandatory, mostly used from developers or in specific model versions under development

4.2 Model outputs

For each simulation the 3D-CMCC-FEM creates ex-novo or rewrites into the output folder a file named "output.txt".

In this folder 4 other subfolders based on time-scale and settings choices should created. These files contain every result for debug (if necessary) daily, monthly and annual time-step simulations. It is also useful to check which model functions have been used. These results can be obtained at stand level or for each type of class level (layer, dbh, age or species class) on Unix like platforms, if you need to extrapolate a variable it is advised to use the "grep" tool.

E.g. open a terminal into the output folder and for the variable NPP type:

```
"cat output.txt | grep 'Stand NPP' "if you want to see grep output into terminal; "cat output.txt | grep 'Stand NPP' > NPP.txt" if you want to redirect grep output into an NPP file inside the output folder
```

<u>IMPORTANT</u>: be sure to use the correct declaration of the output as grep parameter.

The Model provides outputs both at class level that at cell level (by summing up or averaging across the classes).

Annual Outputs

At class level:

reser_as_diff

ResAlloc

ResDeple

ResUsage

YEAR	Year of simulation
LAYER	Layer of tree class
HEIGHT	Average height of a species (m)
DBH	Average diameter at breast height of a species (cm)
AGE	Age of trees (years)
SPECIES	Tree Species
MANAGEMENT	T = Timber
GPP	Yearly Gross Primary Production (gC m ⁻² year ⁻¹)
GPP_SUN:GPP	Yearly Gross Primary Production for sun leaves (gC m ⁻² year ⁻¹)
GPP_SHADE:GPP	Yearly Gross Primary Production for shaded leaves (gC m ⁻² year ⁻¹)
v_SUN:A_SUN	Carboxylation rate/Final assimilation rate ratio for sun leaves
Aj_SUN:A_SUN	RuBP regeneration/Final assimilation rate ratio for sun leaves
Av_SHADE:A_SHADE	Carboxylation rate/Final assimilation rate ratio for shaded leaves
Aj_SHADE:A_SHADE	RuBP regeneration/Final assimilation rate ratio for shaded leaves
Av_TOT:A_TOT	Carboxylation rate/Final assimilation rate ratio
Aj_TOT:A_TOT	RuBP regeneration/Final assimilation rate ratio
GR	Growth respiration (gC m ⁻² year ⁻¹)
MR	Maintenance Respiration (gC m ⁻² year ⁻¹)
RA	Autotrophic respiration (gC m ⁻² year ⁻¹)
NPP	Net Primary Production (gC m ⁻² year ⁻¹)
BP	Yearly Biomass Production (gC m ⁻² year ⁻¹)



Annual reserve allocated (tNSC cell⁻¹ year⁻¹)

Annual reserve depleted (tNSC cell⁻¹ year⁻¹)

Annual reserve used (tNSC cell⁻¹ year⁻¹)

BP/NPP Biomass productivity vs. Net Primary Production
ResAlloc/NP Annual reserve allocated vs. Net Primary Production
ResAlloc/BP Annual reserve allocated vs. Biomass productivity
ResDeple/NPP Annual reserve depleted vs. Net Primary Production

ResDeple/BP

Annual reserve depleted vs. Biomass productivity

ResUsage/NPP

Annual reserve used vs. Net Primary Production

ResUsage/BP

Annual reserve used vs. Biomass productivity

CUE

Annual Carbon Use Efficiency (gC NPP gC GPP⁻¹)

BPE

Biomass Production Efficiency (gC BP gC GPP⁻¹)

diffCUE-BPE CUE - BPE Y(PERC) RA/GPP * 100

PeakLAI Peak LAI (maximum attainable LAI) (m²m⁻²)

MaxLAI Maximum of LAI (maximum reached LAI) (m²m⁻²)

SLA Specific Leaf Area (m²Kg⁻¹)

SAPWOOD_AREA Tree sapwood area (cm²)

CC-Proj Projected Canopy Cover (frac)

DBH/Crown diameter relationship

CROWN HEIGHT Crown Height (m)

CROWN DIAMETER

CROWN_AREA_PROJ Crown Projected Area (at zenith angle) (m²)

APAR Absorbed Photosynthetically Active Radiation (molPARm⁻²year⁻¹)

Crown Projected Diameter (m)

LIVETREE Number of live trees (ntree cell⁻¹)

DEADTREE Number of dead trees (ntree cell⁻¹)

THINNEDTREE Number of thinned trees (ntree cell⁻¹)

VEG_D Annual number of vegetative days (days year⁻¹)
FIRST_VEG_DAY First annual day of vegetative period (DIM)
CTRANSP Canopy Transpiration (mm m⁻²year⁻¹)
CINT Canopy Interception (mm m⁻²year⁻¹)

CINT Canopy Interception (mm m ²year ²)

CLE Canopy Latent Heat (W m ²year ²)

WUE Annual Water Use Efficiency (DIM)

MIN_RESERVE_C Current Minimum reserve carbon pool (tC cell⁻¹)

RESERVE_C Current Reserve carbon pool (tC cell⁻¹)
STEM_C Current Stem carbon pool (tC cell⁻¹)

STEMSAP_C Current Stem sapwood carbon pool (tC cell⁻¹)
STEMHEART_C Current Stem heartwood carbon pool (tC cell⁻¹)

STEMSAP_PERC Stem Sapwood vs. Total Stem (%age)

STEMLIVE_C Current Stem live wood carbon pool (tC cell⁻¹)
STEMDEAD_C Current Stem dead wood carbon pool (tC cell⁻¹)

STEMLIVE_PERC Live stem vs. Total stem (%age)

MAX_LEAF_C Maximum Current Leaf carbon pool (tC cell ⁻¹year⁻¹)
MAX_FROOT_C Maximum Current Fine Root carbon pool (tC cell ⁻¹year⁻¹)

CROOT_C Current Coarse Root carbon pool (tC cell⁻¹)

CROOTLIVE_C Current Coarse root live wood carbon pool (tC cell⁻¹)
CROOTDEAD_C Current Coarse root dead wood carbon pool (tC cell⁻¹)

CROOTLIVE_PERC Live Coarse Root vs. Total stem (%age)
BRANCH_C Current Branch carbon pool (tC cell⁻¹)

BRANCHLIVE_C Current Branch live wood carbon pool (tC cell⁻¹)
BRANCHDEAD_C Current Branch dead wood carbon pool (tC cell⁻¹)

BRANCHLIVE_PERC Live Branch vs. Total stem (%age)



FRUIT_C

MAX_FRUIT_C

Annual Fruit carbon pool (tC cell⁻¹)

RESERVE_N

Current Reserve nitrogen pool (tC cell⁻¹)

STEM_N

Current Stem nitrogen pool (tC cell⁻¹)

STEMLIVE_N

Current Live Stem nitrogen pool (tN cell⁻¹)

STEMDEAD_N

Current Dead Stem nitrogen pool (tN cell⁻¹)

CROOT_N

Current Coarse Root nitrogen pool (tN cell⁻¹)

CROOTLIVE_N Current Coarse root live wood nitrogen pool (tN cell⁻¹)
CROOTDEAD N Current Coarse root dead wood nitrogen pool (tN cell⁻¹)

BRANCH_N Current Branch nitrogen pool (tN cell⁻¹)

BRANCHLIVE_N Current Branch live wood nitrogen pool (tN cell⁻¹)
BRANCHDEAD_N Current Branch dead wood nitrogen pool (tN cell⁻¹)

FRUIT_N Current Fruit nitrogen pool (tN cell⁻¹)

STANDING_WOOD Standing wood carbon (tC cell⁻¹)

DELTA_WOOD Annual wood increment (tC cell⁻¹year⁻¹)

CUM_DELTA_WOOD Cumulated annual wood increment (tC cell⁻¹year¹)

BASAL_AREA Individual basal area (m²ha-¹)

TREE_CAl Single Tree Current Annual Volume Increment (m³tree⁻¹year¹)
TREE_MAI Single Tree Mean Annual Volume Increment (m³tree⁻¹year¹)

CAI Current Annual Volume Increment (m³class⁻¹year⁻¹)

MAI Mean Annual Volume Increment (m³class⁻¹year⁻¹)

VOLUME

Stem volume (m³class¹)

TREE_VOLUME

Single tree volume (m³tree¹)

DELTA TREE VOL (perc)

Tree volume increment (%)

DELTA_AGB Aboveground biomass increment (tCcell⁻¹year⁻¹)
DELTA_BGB Belowground biomass increment (tCcell⁻¹year⁻¹)

AGB Aboveground Biomass pool (tC cell⁻¹)
BGB Belowground Biomass pool (tC cell⁻¹)

BGB.AGB BGB/AGB

DELTA_TREE_AGB

Aboveground biomass increment (tC cell⁻¹year⁻¹)

DELTA_TREE_BGB

Belowground biomass increment (tC cell⁻¹year⁻¹)

C_HWP Annual harvested woody products removed from (tC cell⁻¹year⁻¹)

VOLUME_HWP Annual volume harvested woody products removed (m³cell⁻¹year⁻¹)

STEM_RA

Leaf autotrophic respiration (gC m⁻²year⁻¹)

LEAF_RA

Leaf autotrophic respiration (gC m⁻²year⁻¹)

FROOT_RA

Fine root autotrophic respiration (gC m⁻²year⁻¹)

CROOT_RA

Coarse root autotrophic respiration (gC m⁻²year⁻¹)

BRANCH_RA

Branch autotrophic respiration (gC m⁻²year⁻¹)

At cell level:

gpp Gross Primary Production (gC m⁻²year⁻¹)
npp Net Primary Production (gC m⁻²year⁻¹)
ar Autotrophic respiration (gC m⁻²year⁻¹)
hr Heterotrophic Respiration (gC m⁻²year⁻¹)
rsoil Soil respiration flux (gC m⁻²year⁻¹)
rsoilCO2

reco Annual ecosystem respiration (gC m⁻²year⁻¹)



22

Раде

^{*}variables may change across the different model versions

nee Annual net ecosystem exchange (gC m⁻²year⁻¹)
nep Annual net ecosystem production (gC m⁻²year⁻¹)
et Annual evapotranspiration (mm m⁻²year⁻¹)

le Latent heat flux (W m⁻²year⁻¹)

soil.evapo

Annual soil evaporation (mm m⁻²year⁻¹)

asw

Current available soil water (mm volume⁻¹)

iWue

Annual intrinsic Water Use Efficiency (DIM)

vol Current volume (m⁻³cell) cum vol Cumulated volume (m⁻³cell)

run_off Current amount of water outflow (runoff) (mm m⁻²year⁻¹)

Litter carbon (gC m⁻²) litrC Litter labile carbon (gC m⁻²) litr1C Litter unshielded carbon (gC m⁻²) litr2C litr3C Litter shielded carbon (gC m⁻²) Litter lignin carbon (gC m⁻²) litr4C Cwd carbon (gC m⁻²) cwd C Cwd unshielded (gC m⁻²) cwd 2C Cwd shielded (gC m⁻²) cwd 3C Cwd lignin (gC m⁻²) cwd 4C soilC Soil carbon (gC m⁻²)

soil1C Microbial recycling pool carbon (fast) (gC m⁻²)
soil2C Microbial recycling pool carbon (medium) (gC m⁻²)
soil3C Microbial recycling pool carbon (slow) (gC m⁻²)
soil4C Recalcitrant SOM carbon (humus, slowest) (gC m⁻²)

litterN Litter nitrogen (gN m⁻²)
litter1N Litter labile nitrogen (gN m⁻²)

litter2N Litter unshielded cellulose nitrogen (gN m⁻²)
litter3N Litter shielded cellulose nitrogen (gN m⁻²)

litter4N Litter lignin nitrogen (gN m⁻²) cwd_N Cwd nitrogen (gN m⁻²)

cwd_2NCwd unshielded nitrogen (gN m-2)cwd_3NCwd shielded nitrogen (gN m-2)cwd_4NCwd lignin nitrogen (gN m-2)soilNSoil nitrogen (gN m-2)

soil1N Microbial recycling pool nitrogen (fast) (gN m⁻²)
soil2N Microbial recycling pool nitrogen (medium) (gN m⁻²)
soil3N Microbial recycling pool nitrogen (slow) (gN m⁻²)
soil4N Recalcitrant SOM nitrogen (humus, slowest) (gN m⁻²)
solar rad Incoming short-wave radiation (MJ m⁻²year⁻¹)

Monthly Outputs

At class level:

YEAR Year of simulation
MONTH Month of simulation
LAYER Layer of tree class

HEIGHT Average height of a species (m)

DBH Average diameter at breast height of a species (cm)

AGE Age of trees (years)



^{*}variables may change across the different model versions

SPECIES Tree species
MANAGEMENT T = Timber

GPP Gross Primary Production (gC m⁻²month⁻¹)

NET_ASS Monthly net assimilation (gC m⁻²month⁻¹)

RA Autotrophic Respiration (gC m⁻²month⁻¹)

NPP Net Primary Production (gC m⁻²month⁻¹)

CUE Monthly Carbon Use Efficiency $(0 \rightarrow 1)$ (gC_{NPP} gC_{GPP}⁻¹)

CTRANSP Canopy Transpiration (mm m⁻²month⁻¹)
CET Canopy Evapotranspiration (mm m⁻²month⁻¹)

CLE Canopy Latent Heat (W m⁻²month⁻¹)

CC Canopy Cover

DBHDC DBH/Crown diameter relationship
HD_EFF Effective Height/Diameter ratio (DIM)

HDMAX Height (m) to Base diameter (m) ratio MAX (DIM)
HDMIN Height (m) to Base diameter (m) ratio MIN (DIM)

N_TREE Number of trees (n tree cell⁻¹) WUE Monthly Water Use Efficiency (DIM) Wres Reserve carbon pool (tC cell⁻¹) Stem carbon pool (tC cell⁻¹) WS WSL Stem live wood pool (tC cell⁻¹) WSD Stem dead wood (tC cell⁻¹) Maximum leaf wood (tC cell⁻¹) **PWL** Maximum fine root wood (tC cell⁻¹) **PWFR** WCR Coarse root biomass (tC cell⁻¹)

WCRL Coarse root live wood biomass (tC cell⁻¹)
WCRD Coarse root deadwood biomass (tC cell⁻¹)

WBB Branch biomass (tC cell⁻¹)

WBBL Branch live wood biomass (tC cell⁻¹)
WBBD Branch dead wood biomass (tC cell⁻¹)

At cell level:

gpp	Gross Primary Production (gC m ⁻² month ⁻¹)
npp	Net Primary Production (gC m ⁻² month ⁻¹)
ar	Autotrophic respiration (gC m ⁻² month ⁻¹)
et	Monthly evapotranspiration (gC m ⁻² month ⁻¹)
le	Latent heat flux (W m ⁻²)
asw	Available soil water (mm volume ⁻¹)
iWue	Intrinsic Water Use Efficiency

^{*}variables may change across the different model versions

Daily Outputs

At class level:

YEAR	Year of simulation
MONTH	Month of simulation
DAY	Day of simulation
LAYER	Layer of forest structure
HEIGHT	Average height of a specie (m)



^{*}variables may change across the different model versions

DBH Average diameter at breast height of a specie (cm)

AGE Age of trees (years)

SPECIES Tree species
MANAGEMENT T = Timber

GPP Gross Primary Production (gC m⁻²day⁻¹)

Av_TOT Carboxylation rate for limited assimilation (μ mol m⁻²s⁻¹) Aj_TOT RuBP regeneration limited assimilation (μ mol m⁻²s⁻¹)

Final assimilation rate (µmol m⁻²s⁻¹) A_TOT RG Growth respiration (gC m⁻²day⁻¹) Maintenance Respiration (gC m⁻²day⁻¹) RM Autotrophic respiration (gC m⁻²day⁻¹) RA Net Primary Production (gC m⁻²day⁻¹) NPP Daily biomass production (gC m⁻²day⁻¹) BP Daily carbon Use Efficiency (gC_{NPP} gC_{GPP}⁻¹) CUE Daily biomass production efficiency (gC m⁻²day⁻¹) **BPE** LAI for Projected Area overed (at zenith angle) (m² m⁻²) LAI PROJ Peak Projected LAI (maximum attainable LAI) (m² m⁻²) PEAK-LAI PROJ

LAI_EXP

LAI for Exposed Area covered (m² m⁻²)

D-CC_P

Projected Canopy Cover (frac)

DBH/Crown diameter relationship

CROWN_AREA_PROJ Crown Projected Area (at zenith angle) (m²)

PAR Photosynthetically Active Radiation (molPAR m⁻²day⁻¹)

APAR Absorbed Photosynthetically Active Radiation (molPAR m²day¹)
fAPAR Fraction of Absorbed Photosynthetically Active Radiation (unitless)

NTREE Number of trees

VEG D Day of vegetative period for class (Days/Year)

INT Canopy Interception (mm m⁻²day⁻¹)

WAT Canopy Water stored (mm m⁻²)

EVA Canopy Evaporation (mm m⁻²day⁻¹)

TRA Canopy Transpiration (mm m⁻²day⁻¹)

ET Canopy Evapotranspiration (mm m⁻²day⁻¹)

LE Canopy Latent Heat (W m⁻²)
WUE Water Use Efficiency (DIM)

RESERVE_C Current Reserve carbon pool (tC cell⁻¹)
STEM_C Current Stem carbon pool (tC cell⁻¹)

STEMSAP_C Current Stem sapwood carbon pool (tC cell⁻¹)
STEMLIVE_C Current Stem live wood carbon pool (tC cell⁻¹)
STEMDEAD C Current Stem dead wood carbon pool (tC cell⁻¹)

LEAF_CCurrent Leaf carbon pool (tC cell-1)FROOT_CCurrent Fine root carbon pool (tC cell-1)CROOT_CCurrent Coarse root carbon pool (tC cell-1)

CROOTSAP_C Current Coarse root sapwood carbon pool (tC cell⁻¹)

CROOTLIVE_C Current Coarse root live wood carbon pool (tC cell⁻¹)

CROOTDEAD C Current Coarse root dead wood carbon pool (tC cell⁻¹)

BRANCH C Current Branch carbon pool (tC cell⁻¹)

BRANCHSAP_C Current Branch sapwood carbon pool (tC cell⁻¹)
BRANCHLIVE_C Current Branch live wood carbon pool (tC cell⁻¹)
BRANCHDEAD_C Current Branch dead wood carbon pool (tC cell⁻¹)

FRUIT_C Current Fruit carbon pool ((tC cell⁻¹)

DELTARESERVE_C Daily allocation to reserve (tC cell⁻¹day⁻¹)



Daily allocation to stem (tC cell⁻¹day⁻¹) DELTA STEM C Daily allocation to leaf (tC cell⁻¹day⁻¹) DELTA LEAF C Daily allocation to fine root (tC cell⁻¹day⁻¹) DELTA FROOT C DELTA_CROOT_C Daily allocation to coarse root (tC cell⁻¹day⁻¹) Daily allocation to branch (tC cell⁻¹day⁻¹) DELTA_BRANCH_C Daily allocation to fruit (tC cell⁻¹day⁻¹) DELTA FRUIT C Current reserve nitrogen pool (tN cell⁻¹) RESERVE N Current stem nitrogen pool (tN cell⁻¹) STEM_N STEMLIVE_N Current Live Stem nitrogen pool (tN cell⁻¹) STEMDEAD N Current Dead Stem nitrogen pool (tN cell⁻¹) Current leaf nitrogen pool (tN cell⁻¹) LEAF_N FROOT_N Current Fine Root nitrogen pool (tN cell⁻¹) CROOT N Current Coarse Root nitrogen pool (tN cell⁻¹)

CROOTLIVE_N Current Coarse root live wood nitrogen pool (tN cell⁻¹)
CROOTDEAD_N Current Coarse root dead wood nitrogen pool (tN cell⁻¹)

BRANCH N Current Branch nitrogen pool (tN cell⁻¹)

BRANCHLIVE_N Current Branch live wood nitrogen pool (tN cell⁻¹)

BRANCHDEAD N Current Branch dead wood nitrogen pool (tN cell⁻¹)

Current Fruit nitrogen pool (tN cell⁻¹) FRUIT N Daily allocation to reserve (tN cell⁻¹day⁻¹) DELTARESERVE N Daily allocation to stem (tN cell⁻¹day⁻¹) DELTA STEM N DELTA_LEAF_N Daily allocation to leaf ((tN cell⁻¹day⁻¹) Daily allocation to fine root (tN cell⁻¹day⁻¹) DELTA FROOT N DELTA_CROOT_N Daily allocation to coarse root (tN cell-1day-1) DELTA_BRANCH_N Daily allocation to branch (tN cell⁻¹day⁻¹) Daily allocation to fruit (tN cell-1day-1) DELTA FRUIT N Stem autotrophic respiration (gC m⁻²day⁻¹) STEM AR Leaves autotrophic respiration (gC m⁻²day⁻¹) LEAL AR FROOT_AR Fine Roots autotrophic respiration (gC m⁻²day⁻¹) Coarse Roots autotrophic respiration (gC m⁻²day⁻¹) CROOT AR Branch autotrophic respiration (gC m⁻²day⁻¹) BRANCH AR F_CO2 CO2 fertilization effect (DIM) (as choiced in script)

F_CO2_VER CO2 fertilization effect (DIM) (Veroustraete's version)
F_CO2_FRA CO2 fertilization effect (DIM) (Franks et al.'s version)
FCO2_TR CO2 fertilization effect (DIM) (for stomatal conductance)

FLIGHT Light modifier FAGE Age modifier $(0\rightarrow 1)$

FT Air temperature modifier $(0 \rightarrow 1)$

FVPD VPD modifier $(0 \rightarrow 1)$

FN Soil nutrient modifier $(0\rightarrow 1)$ FSW Soil water modifier $(0\rightarrow 1)$

LITR_C Current Litter Carbon Pool (tC cell⁻¹)
CWD_C Coarse Woody Debris Carbon (tC cell⁻¹)

At cell level:

gpp	Gross Primary Production (gC m ⁻² day ⁻¹)	
npp	Net Primary Productivity (gC m ⁻² day ⁻¹)	
ar	Autotrophic respiration (gC m ⁻² day ⁻¹)	
hr	Heterotrophic respiration (gC m ⁻² day ⁻¹)	
	<u>.</u>	



^{*}variables may change across the different model versions

Soil respiration flux (gC m⁻²year⁻¹) rsoil Daily ecosystem respiration (gC m⁻²day⁻¹) reco Daily net ecosystem exchange (gC m⁻²day⁻¹) nee Daily net ecosystem production (gC m⁻²day⁻¹) nep Daily evapotranspiration (mm m⁻²day⁻¹) et Daily latent heat flux (W m⁻²) le Daily soil evaporation (mm m⁻²day⁻¹) soil evapo Current Amount of Snow (Kg m⁻²) snow pack asw Current available soil water (mm volume⁻¹) moist ratio Soil moisture ratio (DIM) iWue Daily intrinsic Water Use Efficiency (DIM) Litter carbon (gC m⁻²) litrC

litr1C Litter labile carbon (gC m⁻²) Litter unshielded carbon (gC m⁻²) litr2C Litter shielded carbon (gC m⁻²) litr3C Litter lignin carbon (gC m⁻²) litr4C Cwd carbon (gC m⁻²) cwd C cwd 2C Cwd unshielded (gC m⁻²) Cwd shielded (gC m⁻²) cwd 3C cwd 4C Cwd lignin (gC m⁻²) Soil carbon (gC m⁻²) soilC

soil1C Microbial recycling pool carbon (fast) (gC m⁻²)
soil2C Microbial recycling pool carbon (medium) (gC m⁻²)
soil3C Microbial recycling pool carbon (slow) (gC m⁻²)
soil4C Recalcitrant SOM carbon (humus, slowest) (gC m⁻²)

litterN Litter Nitrogen (gN m⁻²)
litter1N Litter labile Nitrogen (gN m⁻²)

litter2N Litter unshielded cellulose Nitrogen (gN m⁻²)
litter3N Litter shielded cellulose Nitrogen (gN m⁻²)

litter4N Litter lignin Nitrogen (gN m⁻²) cwd N Cwd Nitrogen (gN m⁻²)

cwd_2NCwd unshielded Nitrogen (gN m-2)cwd_3NCwd shielded Nitrogen (gN m-2)cwd_4NCwd lignin Nitrogen (gN m-2)

soilN Soil Nitrogen (gN m⁻²)

soil1NMicrobial recycling pool Nitrogen (fast) (gN m-2)soil2NMicrobial recycling pool Nitrogen (medium) (gN m-2)soil3NMicrobial recycling pool Nitrogen (slow) (gN m-2)soil4NRecalcitrant SOM Nitrogen (humus, slowest) (gN m-2)

tsoil Soil Temperature (°C)

daylenght Day length

5. Management

The model simulates several management practices on high stands, while coppice management is still under development. Three different management practices can be simulated by 3D-CMCC-FEM. For each treatment the user can specify intensity, interval and rotation age.

There are three main settings for management:

• "man on": the model will simulate the management as set in the species.txt file (e.g.



ge 27

^{*}variables may change across the different model versions

Fagus_sylvatica.txt), for example the thinning.

• "man var": the model simulates the observed management (the thinning as observed in the changes of stand density in the stand file "input.txt") and then simulates the thinning interval and final harvesting at the years taken from an external table (NAMESITE_management.txt) but with the intensity as in the *species.txt* file (e.g. Fagus_sylvatica.txt). Note, in this case mortality is not simulated at all.

"man off": no management will be applied.

6. 3D-CMCC-FEM Usage

3D-CMCC-FEM is a command line program, and its behaviour is controlled by several command line options:

*-i input path	i.e.: -i c:\input\directory\
*-o output path	i.e.: -o c:\output\directory\
*-p parameterization directory	i.e.: -i c:\parameterization\directory\
-d dataset filename stored into input directory	i.e.: -d input.txt
-m met filename list stored into input directory	i.e.: -m meteo.txt or meteo.nc
-s soil filename stored into input directory	i.e.: -s soil.txt or soil.nc
-t topo filename stored into input directory	i.e.: -t topo.txt or topo.nc
-c settings filename stored into input directory	i.e.: -c settings.txt
-k CO ₂ atmospheric concentration file	i.e.: -k co2_conc.txt
-n ndep file	i.e.: -n ndep.txt
-r output vars list	i.e.: -r output_vars.lst
-u benchmark path	(for model developers)
-h	print this help

^{*}Parameters NOT mandatory, mostly used from developers or in specific model versions under development

More specifically:

-i	This is not a mandatory parameter. if not used, input files will be searched where program is.
-0	This is not a mandatory parameter. If not used, output files will be created where program is.
-p	This is not a mandatory parameter. If not used, parameterization file will be searched where program is.



-d "stand"

This file will be searched in input path, if specified. It can be an ASCII or NETCDF file. You can use '//' for comment it. ASCII file must have following header, separated by a comma:

Mandatory parameters: "Year, x, y, Age, Species, Management, N, Stool, AvDBH, Height"

NOTE: Please see [SPECIES]* section and [MANAGEMENT]** section to check allowed values. Same columns name applies to variables name in NETCDF version of file.

-m "meteo"

This file will be searched in input path, if specified. It can be an ASCII or NETCDF file. You can specify a .lst (list) file if you have separated values.

List file must contain the name of NETCDF files to import, one row for variable e.g.:

6 WS f 2000 2001 123 456.nc

6_TOT_PREC_2000_2001_123_456.nc

6_SWC_2000_2001_123_456.nc

6_TMAX_2M_2000_2001_123_456.nc

6_TMIN_2M_2000_2001_123_456.nc

6_TSOIL_2000_2001_123_456.nc

6_VPD_2000_2001_123_456.nc

6_ET_2000_2001_123_456.nc

6_LAI_2000_2001_123_456.nc

6_RADS_2000_2001_123_456.nc

ASCII file must have following header, separated by a tab (/t):

Mandatory parameters: "Year, Month, n_days, Rg_f, Ta_f, Tmax, Tmin, Rh_f, Ts_f, Precip, SWC, LAI, ET, WS_f"

Same columns name applies to variables name in NETCDF version of file.

-s "soil"

This file will be searched in input path, if specified.

It can be an ASCII or NETCDF file. ASCII file must have following header, separated by a comma:

Mandatory parameters: "X, Y, LANDUSE, LAT, LON, CLAY_PERC, SILT_PERC, SAND_PERC, SOIL_DEPTH, SOIL_DEPTH, FR, FN0, FNN, M0, LITTERC, LITTERN, SOILC, SOILN, DEADWOODC"

Please see [LANDUSE] section to check allowed values. Same columns name applies to variables name in NETCDF version of file.



-t "topography"

This file will be searched in input path, if specified.

It can be an ASCII or NETCDF file.

ASCII file must have following header, separated by a comma

Mandatory parameters: "X, Y, ELEV"

Same columns name applies to variables name in NETCDF version of file.

-c "model setting"

This file will be searched in input path, if specified.

It must be an ASCII file. You can put comment using '//' token;

NOTE: the file must contain the rows described in the "Settings file" section.

-k "[CO2]"

This file will be searched in input path, if specified.

It must be an ASCII file and must have following header, separated by a tab (/t):

Mandatory parameters: "year (/t) CO2 ppm"

NOTE: mandatory parameter only if "CO2_trans" in settings file is set on 'on' or 'var'

-n "N deposition"

This file will be searched in input path, if specified.

It must be an ASCII file and must have following header, separated by a tab (/t):

Mandatory parameters: ""year (/t) ndep"

NOTE: mandatory parameter only if "Ndep_fixed" in settings file is set on 'off'

-r

this is **not** a mandatory parameter. Use it if you want export variables values inside a NETCDF file.

You can specify more variables per row using a comma as delimiter. Each variable must

have "daily_", "monthly_" or "annual_" prefix. i.e.:

daily_gpp, annual_GPP, daily_ar, monthly_ar, annual_npp

In previous example, daily values for GPP and AR are exported. Monthly values for AR are exported and annual values for GPP and NPP are exported. Files will be created in output path if any or where program is.

[SPECIES]*

Following species can be used on relative column inside an ASCII dataset (without indexes)

NOTE: Please note that you must use their indexes if you use a NETCDF file.

0,Fagussylvatica

1,Castaneasativa

2,Larixdecidua

3,Piceaabies

4,Pinussylvestris

5,Quercuscerris

6,Quercusilex



30 age

7,Quercusrobur 8, quercus_deciduous 9,quercus_evergreen

[MANAGEMENT]**

Following type of management can be used on relative column inside as ASCII dataset (without indexes).

NOTE: Please note that you must use their indexes if you use a NETCDF file.

T is for timber

C is for Coppice (under development)

0,T 1.C

[LANDUSE]***

Following type of landuse can be used on relative column inside as ASCII dataset (without indexes).

Please note that you must use their indexes if you use a NETCDF file.

F is for Forest

Z is for Crop (currently not implemented)

0,F 1,Z

7. How to run and develop the 3D-CMCC-FEM

7.1 Code characteristics

3D-CMCC-FEM was primarily developed on UNIX-Linux with Eclipse IDE Platforms and is compiled using GNU GCC 4.7.2.

<u>IMPORTANT</u>: Be sure to execute 3D-CMCC-FEM on a Linux machine with architecture X86_64 (64 bit), otherwise you firstly need to rebuild code to obtain the object files needed for runs.

7.2 Eclipse usage instruction (for developers)

To Run or to modify (develop the model we suggest using Eclipse CDT simply following these steps (be sure if you choose to use Eclipse, to have installed Git and Egit and to have an internet connection):

- 1) Save the 3D-CMCC-FEM Model (https://github.com/Forest-Modelling-Lab/3D-CMCC-FEM) directory in the path you are going to use as Eclipse Workspace;
- 2) to prevent error from NETCDF libraries, open terminal and type:
 - \$ sudo apt-get install netcdf-bin
 - \$ sudo apt-get install libnetcdf-dev
- 3) To make the model work under Eclipse CDT (any version) using Git follow these steps:
 - download from terminal Git and build-essential
 - o \$ sudo apt-get install build-essential
 - o \$ sudo apt-get install git



download from Ubuntu software center jre 7-8 or jdk (if not installed)

```
o $ sudo apt-get install default-jdk
```

- 4) Download from Eclipse site the most recent version of Eclipse IDE for C/C++ Developers (https://www.eclipse.org/downloads/packages/)
- 5) Open Eclipse and set your Workspace as the same path in which you've placed the Model's folder to do so click on File, then "switch Workspace" and click on "Other..."; here input your current path;
- 6) File -> Import -> Git -> Projects from Git -> Clone Url and in URL please paste the code version you find over the GitHub https://github.com/Forest-Modelling-Lab/3D-CMCC-FEM

For NETCDF file you need to add libraries within eclipse through:

Project->Properties->C/C++ Build->Settings->Cross G++ Linker->Libraries-> in Libraries (-I) add "netcdf"->OK

How to increase Eclipse available heap size (optional)

Some JVMs put restrictions on the total amount of memory available on the heap. If you are getting *OutOfMemoryErrors* while running Eclipse, the VM can be told to let the heap grow to a larger amount by passing the -vmargs command to the Eclipse launcher (http://wiki.eclipse.org/FAQ How do I increase the heap size available to Eclipse%3F).

Here follows a short how to:

- 1) Search for the location of your eclipse.ini file (usually usr/lib/eclipse);
- 2) Open eclipse.ini using gedit command from terminal as super user (sudo gedit eclipse.ini);

BE EXTREMELY CAREFUL TO FOLLOW ECLIPSE DEVELOPERS RULES

Each option and each argument to an option must be on its own line.

All lines after -vmargs are passed as arguments to the JVM, so all arguments and options for eclipse must be specified before -vmargs (just like when you use arguments on the command- line).

Any use of -vmargs on the command-line replaces all -vmargs settings in the .ini file unless – launcher .appendVmargs is specified either in the .ini file or on the command-line. (doc):

in line 12 change -Xms40m into -Xms512m (just replace 40 with 512 without changing the rest of the line).

in line 13 change -Xmx256m into -Xmx1024m (just replace 256 with 11024 without changing the rest of the line)

save eclipse.ini and restart eclipse.

How to work on Eclipse for bash scripts (optional)

To work in Bash Shell scripts within the Eclipse IDE you need to install ShellED eclipse package through the web.

7.3 Bash launch (for UNIX users)

If you are interested only in running the 3D-CMCC-FEM with no interest in developing the model code you can either run the model code in the terminal (i.e. Bash) once check that you have the executable (in Debug or Release folder) build for your OS (be careful that it fits with your architecture: i.e. 36 or 64 bit) through:

o ./3D CMCC Forest Model ...,





Figure 8 Launching the model in Bash

8. Questions or comments

Shall you have issues with the code or for any suggestions, please let us know. For any questions on how to parameterize or run the code, please read this file first.

Contacts:

The laboratory	forest.modelling.lab@gmail.com
The developers	3d_cmcc_fem@gmail.com
<u>Alessio Collalti</u>	✓alessio.collalti@cnr.it
<u>Daniela Dalmonech</u>	daniela.dalmonech@isafom.cnr.it
<u>Riccardo Testolin</u>	riccardo.testolin@isafom.cnr.it
<u>Gina Marano</u>	ginamarano.forest@gmail.com

Version updated: 18 February, 2023

